



# Thesys iPad Edition



## User Manual

What is Thesys? .....	4
<b>Getting Started</b> .....	<b>5</b>
<b>Setting up Thesys</b> .....	5
Getting Some Sound .....	5
Loading Presets .....	6
Saving Presets .....	6
Deleting Presets .....	6
Sharing Presets via iCloud Drive .....	6
Playing another Instrument .....	7
MIDI Clock Sync .....	8
BPM Control .....	8
MIDI File Save .....	8
<b>Connectivity</b> .....	<b>10</b>
iCloud Synchronization .....	10
MIDI .....	11
Ableton Link .....	11
<b>Host Integration</b> .....	<b>12</b>
<b>Thesys iPad Settings</b> .....	<b>17</b>
Audio Settings .....	17
MIDI Settings .....	18
iCloud Synchronization .....	18
Ableton Link .....	18
Zoom .....	19
<b>Control Section</b> .....	<b>20</b>
<b>Global Controls</b> .....	20
Open Manual .....	20
MIDI Activity Indicators .....	20
MIDI IN/MIDI OUT transposition .....	20
Transpose Mode .....	20
Synthesizer/MIDI Settings toggle switch .....	21
<b>Sequencer Settings</b> .....	21
Trigger By .....	21
Trigger Mode .....	22
Loop .....	22
Tempo Division Unit .....	22
Swing Amount .....	22
<b>Action Section</b> .....	23
Gate Time .....	23
Velo Gate .....	24
Looper .....	24

Slow Down .....	24
Retrigger .....	24
Half Speed .....	25
Manual Step .....	25
Mute .....	25
<b>Start/Stop Button</b> .....	25
<b>Pattern Sequencer</b> .....	25
on/off .....	26
Loop Bar .....	26
Pattern Change Speed .....	26
Pattern Select .....	26
Number of Repeats .....	26
<b>Keyboard Control Section</b> .....	27
Keyboard Control Quantization Value .....	27
Pattern Select .....	27
Action Section (Keys) .....	27
Pitch Transposition .....	28
<b>Sequencer Section</b> .....	29
Sequencer Preset .....	29
Preset vs. Pattern .....	29
Global Sequencer Controls .....	29
Common Controls and Functions .....	31
Pitch .....	35
Velocity .....	37
Gate Time .....	38
Performance .....	39
Modulation .....	41
<b>Built-in Synthesizer</b> .....	43
Synthesizer Preset Manager .....	43
Filter .....	44
Delay .....	45
Appendix .....	46
Chords .....	48
FAQ .....	56
Contact .....	56

## What is Thesys?

Thesys is an extremely powerful and intuitive MIDI sequencer, giving you control over just about all aspects of your favorite MIDI devices. Use Thesys to create varied and organic bass lines, screaming leads, pulsating chords, and organic pad sounds in the studio or on stage. Sequence and send patterns of just about any MIDI data you want, not just pitch and velocity. For example, you can include things like Program Change, Portamento, Aftertouch, and any other MIDI CC in your sequences.

For live musicians, Thesys provides an extremely versatile palette of performance options which can be triggered right from your MIDI keyboard: you can transpose, manipulate, twist up, mutate, and mangle your patterns without even getting near your computer.

No other MIDI sequencer plugin offers you the ease and power of Thesys. It is 100% MIDI compliant and therefore provides the ultimate MIDI sequencing solution.

# Getting Started

This section will show you how to get a few sounds out of Thesys to give a feel for how things work. All of the functions mentioned in this section are described in detail in the sections in this manual which then follow.

## Setting up Thesys

### Getting Some Sound

Let's start from scratch. At the top of the Thesys Window (to the right of the Thesys logo), you'll see the current preset name. Press on the name to open the preset chooser and call up the INIT preset from the «Factory1» folder there.

Press on the Start button in the lower right corner. The sequencer engine begins to run, but you won't hear any sound because the INIT preset's Velocity sequencer is filled with 0 values. Draw or press in the Velocity sequencer area and you'll hear some 16th notes.

Create a more melodic pattern by changing the values in the Pitch Sequencer. You may want to slow the step speed down by selecting eighth notes instead of sixteenth notes with the Tempo Selector in the Sequencer Settings section.

In the INIT preset, the Sequencers' loop lengths are all set to 8 steps. To keep things all synced up, in the Sequencer Settings section, set the "Loop" toggle to global. This just means that all the different sequencers will all have Loop lengths which will be identical to that of the Pitch sequencer at the very top.

Grab the right-hand edge of the Loop Bar and drag it out towards the right to create a longer loop (try 16 steps, for example). For the additional steps, you'll have to draw in some Velocity Sequencer steps in order to get sound for the whole length of your pattern.

Now try playing with the Gate Time Sequencer. By default, each step is set to a value of 1.0, meaning that the note will be "on" for the duration of the step. To understand how the Gate Sequencer works, slide a few steps way up to the maximum of 4.0. If there are consecutive steps with this value, you'll hear overlapping notes, because steps will be triggered while the gate is still "open" for previous notes. This works with the internal synth as well as any other polyphonic synth being driven by Thesys.

Pull some other steps way down and notice the short impulse-like sounds which result. Using intermediate values closer to 1.0 will give your lines more variety and make them sound more organic.

Once you've tweaked your pattern a bit, try out some Actions:

With the sequencer engine running, press on the Looper in the Action Section. Adjust the length of the Looper with the Steps knob. Try Half Speed, Mute, and the other Actions to get a feel of the some of the performance possibilities.

## Loading Presets

Press on the current preset name at the top of the Thesys Window to open the preset chooser to choose a preset from within one of the preset categories.

To the left and right of the Preset Manager are arrows allowing you to step through presets consecutively.

## Saving Presets

To save a preset, open the preset browser and press SAVE.

## Deleting Presets

To delete a preset, press DELETE and choose the preset you want to delete. Confirm by pressing the DELETE button. (Please note that only User presets and Midi Program presets can be deleted.)

## Sharing Presets via iCloud Drive

In order to get hold of the presets created on the iPad and to share them accross multiple devices you must set up iCloud in the [Thesys Settings](#).

[BACK TO TABLE OF CONTENT](#)

## Playing another Instrument

The fun with Thesys really begins when you start using its MIDI output to drive other instruments.



The first thing we'll do is turn off the internal synthesizer.


To do this, open the synth by pressing on the Loudspeaker icon just to the right of the Velocity Sequencer to toggle to the Synthesizer section.



Below the Sugar Bytes logo in the top right area, press on the on/off switch to turn the Synthesizer off.

If you want to **use the Thesys to control another synth within your mobile Host** please have a look [here](#) or into the respective iHost manual, to see how to route the MIDI out channel of an instrument to another synth.

If you're using the **Standalone version** of Thesys just tap the **jack symbol** to pick up your target instrument from the list of Audio Unit Instruments. Press the instrument logo to open its GUI. Long press the jack symbol to unplug an instrument.



Target synth standalone apps will be listed under Destinations in the [MIDI settings dialogue](#) of the Thesys standalone. If a synth is connected via the MIDI destination menu, you can choose all available channels of the synth. You can open other MIDI channels with other soft synths (or samplers) and set similarly. This way you can achieve layers of sounds, all triggered by Thesys.

[BACK TO TABLE OF CONTENT](#)

## MIDI Clock Sync

Thesys can act as receiver and sender of MIDI clock signals.  
As a master start, stop and clock ticks will be sended.

As a receiver Start, Stop, Continue, Song Position Pointer and Clock ticks will be processed. The tempo will be calculated automatically.

## BPM Control



Tap, swipe left/right the BPM Control panel to match the tempo or long press the BPM Control to manually set up the tempo.

## MIDI File Save




The MIDI data generated by Thesys can be saved to a MIDI file. Just press the MIDI File Save button and the file will be created at the same level as the Contents folder of Thesys.

Use the control below to set the length of the MIDI file. The maximum length is 64 bars. Since the file will be written on the fly, Thesys will not produce sound while the file is generated.

## MIDI Program Change

All presets in the Midi Programs folder can be called with MIDI Program Change messages.



Press “Copy to Midi Programs” at the bottom of the Preset Browser and select the presets you want to copy to the “Midi Programs” folder. Confirm by pressing “Copy to Midi Programs” again. Now you should see the presets under “Midi Programs”.

# Connectivity

[iCLOUD SYNCHROSIZATION](#)

[MIDI](#)

[ABLETON LINK](#)

[USING THESYS TO CONTROL ANOTHER SYNTH](#)

[HOST INTEGRATION](#)

## iCloud Synchronization

Through iCloud, you'll be able to share your saved presets across multiple devices including your desktop computer.

This feature is disabled by default. To sync Thesys across your devices, launch the [Thesys Settings](#).


There choose iCloud, tap iCloud and set iCloud to On. Once activated, presets you save in the Thesys iOS version are synced automatically to your iCloudDrive.

To share a preset from your **Thesys iOS version to your computer**, you'll need to drag and drop or copy/paste the preset from `iCloudDrive/Thesys/Presets/User` into `~/Documents/Sugar Bytes/Thesys/Presets/User`

To share a preset from your **computer to your Thesys iOS version**, you'll need to drag and drop or copy/paste the preset from `~/Documents/SugarBytes/Thesys/Presets/User` into `iCloudDrive/Thesys/Presets/User`

The presets will then automatically appear in the User folder of Thesys' preset browser.

Please note that creating and then reading out a subfolder is technically not possible.



[BACK TO TABLE OF CONTENT](#)


## MIDI

Thesys can receive MIDI from any source (incl. virtual MIDI).

The [MIDI Settings dialogue](#) will show you all MIDI devices currently connected to your iPad.

### MIDI LEARN

All relevant Thesys parameters can be remoted with MIDI CC's and Host Automation.



Press and hold the MIDI learn button to be found in the [General Editing Features](#) (at the bottom of Thesys) and press a control to learn a MIDI CC for it or tap Clear to delete the assignment.

## Ableton Link

Ableton's Link Kit enables you to sync with other apps, other iOS devices and Ableton Live. Call up the dialogue on the Settings page [here](#).

# Host Integration

CUBASIS

AUM

BEATMAKER

AUDIOBUS


APEMATRIX

## Why are there two types of Thesys shown (Thesys and Thesys MIDI FX)?

Most Hosts do not support direct MIDI out of a regular AUv3 instrument and there is no easy way for a plug-in to send MIDI directly to the instrument on the same track/channel. Now with the MIDI FX version of Thesys you get MIDI out "directly" on the track - no routing needed, just place it before the desired instrument and you're good to go! On playback, your recorded MIDI performance is routed through the MIDI FX. The MIDI you play comes in first through Thesys MIDI FX, then from Thesys to the instrument, then out of the instrument to be processed with Audio.

## USING THESYS TO CONTROL ANOTHER SYNTH INSIDE CUBASIS 2

Go to the Inspector panel of your target instrument track and choose Thesys MIDI FX from the MIDI FX tab. Notes and events generated by Thesys will now be sent to your target instrument.




[BACK TO TABLE OF CONTENT](#)

## USING THESYS TO CONTROL ANOTHER SYNTH INSIDE AUM

Create a new channel, tap the “Audio Unit Extension” category and select Thesys MIDI FX. Create another AUM channel and load your target instrument.

Open the target instrument’s MIDI settings panel and select Thesys MIDI FX to route the MIDI output of Thesys to the MIDI input of your target instrument.


Notes and events generated by Thesys will now be sent to your target instrument.



[BACK TO TABLE OF CONTENT](#)

# USING THESYS TO CONTROL ANOTHER SYNTH INSIDE BEATMAKER 3

Go to the Performance View and select the bank of your target instrument (here Bank A1). Open the "MIDI FX" tab at the bottom left hand side, press "ADD MIDI EFFECT" and select Thesys MIDI FX. Notes and events generated by Thesys will now be sent to your target instrument.




[BACK TO TABLE OF CONTENT](#)

## USING THESYS TO CONTROL ANOTHER SYNTH INSIDE AUDIOBUS 3

Select the "MIDI" section in Audiobus, open the "INPUT" and choose Thesys MIDI FX from the "Audio Unit" list. Insert your target instrument in the "OUTPUT" slot.

Notes and events generated by Thesys will now be sent to your target instrument.



[BACK TO TABLE OF CONTENT](#)

## USING THESYS TO CONTROL ANOTHER SYNTH INSIDE APEMATRIX


Go to the Audio Routing Matrix and tap the “+” sign (in the vertical column on the left) to pick up Thesys MIDI FX from the list of Audio Unit MIDI Effects.

Tap OK in the Remote Audio Unit popup window and then turn On the power button (on the right side in the matrix grid).

Hit another “+” sign, load your target instrument and route it to the Audio Output (speaker icon).

Now tap the MIDI Patchbay Icon at the bottom of the matrix to open the MIDI Routing Matrix. Route the MIDI Output from Thesys to the MIDI Input of your target instrument.

Notes and events generated by Thesys will now be sent to your target instrument.



[BACK TO TABLE OF CONTENT](#)

# Thesys iPad Settings



Adjust the way Thesys operates in certain MIDI and Audio connections, enable or disable Ableton link as well as preset file sharing between Thesys iOS and your computer via iCloud synchronization.

## Audio Settings



### Output

If a multichannel sound card is connected, you can choose all available out ports here.

### Latency

This allows you to change the audio latency of Thesys.

If you experience crackles in the audio signal, you should use a larger buffer size.

### Run Audio in Background

Choose Thesys to continue playing even if another app is on or not.

[BACK TO TABLE OF CONTENT](#)

## MIDI Settings

This list shows all MIDI devices currently connected to your iPad.

Supported MIDI Types:

- CoreMIDI virtual ports (to/from other apps)
- CoreMIDI network (as a session originator or receiver to/from Mac or PC)
- CoreMIDI physical devices (USB MIDI Controller)
- Bluetooth MIDI



## iCloud Synchronization


Enable or disable preset file sharing between Thesys iOS and your computer via [iCloud synchronization](#).

## Ableton Link

Hop on to the same network and jam with others using multiple devices running Ableton Link-enabled software. Anyone can start and stop their part while others keep playing. And anyone can adjust the tempo and the rest will follow.

When activated, Ableton Link will sync tempo across apps.

Find out more about Ableton Link [here](#).



[BACK TO TABLE OF CONTENT](#)

## Zoom

Double press an empty area in the instrument in order to zoom in or out.  
We also implemented a « Zoom lock » button.  
Just press on the « loupe » at the bottom left of Thesys to



enable the zoom functionality



lock the zoom functionality

# Control Section

## Global Controls



The Global Controls section consists of all parameter controls in the dark area located outside of the main Sequencer window.

### Open Manual

Pressing on the Open Manual button automatically opens the Thesys manual which was installed with the software. The manual is located within the Thesys application folder and can be copied or moved elsewhere. Keep in mind, however, that the manual cannot be automatically opened with the Open Manual button if it is moved from the original location.

### MIDI Activity Indicators

The MIDI Activity Indicators light up when MIDI is either received by or transmitted from Thesys.

### MIDI IN/MIDI OUT transposition

Just under the MIDI Activity Indicators, the Transposition controls allow you to transpose incoming MIDI notes as well as the MIDI notes transmitted by Thesys. MIDI IN transposition is useful for setting up your controller keyboard for pattern selection and action triggering. Press and drag to change values.

The MIDI OUT octave transposition moves the outgoing MIDI notes up or down up to two octaves. Underneath the octave transposition control, step transposition allows you to move pitches up to 12 half-steps (semi-tones) up or down.

### Transpose Mode

The Transpose Mode switch toggles between ROOT KEY and IN SCALE and determines if incoming MIDI notes transpose the pitch sequence by just moving the root key chromatically (set by the Root Key Control) or are forced into the closest possible note on the scale (determined by the Scale Control).


[BACK TO TABLE OF CONTENT](#)

## Synthesizer/MIDI Settings toggle switch



Press on the speaker icon (on the right edge of the Pitch Sequencer) to toggle between Synthesizer controls and Sequencer Global Settings panel.

## Sequencer Settings



### Trigger By

The Trigger By switch toggles between the Pattern Keys and Pitch Keys as input triggers. In other words, you can set Thesys into motion with either the pitch keys or the pattern keys on your external MIDI keyboard. The keyboard mapping of the pitch keys and pattern keys is shown at the lower edge of Thesys in the Keyboard Control Section (see below: "Keyboard Control Section"). You can also trigger Thesys by simply pressing on the keys.

[BACK TO TABLE OF CONTENT](#)

## Trigger Mode

This three-state toggle switch determines how Thesys responds to a trigger signal. The first option is Host. This means that Thesys is slaved to the host clock and will start when the host clock is started.

Note On triggers (starts) Thesys as soon as a note is played. Thesys continues to play as long as the note is held.

Note Toggle toggles (starts and stops) Thesys with any incoming MIDI note. The first note starts the sequencer and the next incoming note stops it.

## Loop

This setting determines if all sequencers have individual Loop Bars (Individual), or if they share the same loop bar (Global). When Global is chosen, the loop from the Pitch Sequencer is used as the Global Loop.


## Tempo Division Unit

Choose between ten different note values to determine the step rate. The quarter note will advance the sequencer one step per (quarter note) beat; an eighth note rate is twice as fast and a half note half as fast. The default setting is the eighth note. This means that at a clock speed of 120 BPM, the step speed will be at an eighth note pace, or at 240 steps per minute. Setting at the half note value (also at 120 BPM) would then result in a rate of 60 steps per minute. Thesys can run in triplet divisions as well.

## Swing Amount

This slider determines the amount of swing which varies from completely straight (even) at the far left, to a dotted rhythm (75%/25% relationship) at the far right. Pulling the slider to the half-way point results in a ternary (triplet) swing.

## Action Section



The Action Section is a fast and intuitive way to "mutate" your patterns, either on stage or in the studio. All of the functions in the Action (Button) Section correspond to those in the Action (Key) Section, found along the lower edge of the Thesys GUI. The main difference is that the Action Key Section shows a keyboard map allowing you to "play" the actions on your MIDI keyboard controller, while the Action Button Section gives you mouse and MIDI CC control.

In addition, the Action Section provides four additional parameter adjustment knobs corresponding to certain Actions (see below).

Each action button (and key) behaves as a "push-on" switch. In other words, the particular Action is only active as long as a button or key is pushed or played. When the button or key is released, the Action stops and the sequence continues as usual.

### Gate Time



The Gate Time button immediately forces the gate time (length) to a single, uniform value for all steps. If this button is not activated, then the gate time of each step is determined by the height of that step in the Gate Time Sequencer. When you press on the Gate Time Button (or play the corresponding key on your MIDI keyboard controller), then the gate times of all the steps will be exactly the same as long as you push the button (or hold down the key).

The Gate Time value is set with the Time knob to the left of the Gate Time button. Extremely short gate times (staccato) can be created by turning the knob completely to the left. Legato gate times — resulting in a connected melodic line — are achieved by turning the knob to the right of the center position.

[BACK TO TABLE OF CONTENT](#)

## Velo Gate



When pushed, the Velo(city) Gate Action only triggers notes which are higher than the velocity set at the Threshold knob to the right of the Velo Gate. Notes with a velocity setting (determined by the Velocity Sequencer) below the threshold value will not be triggered and the step will be "empty," behaving as if there was no velocity trigger at all. This is a good way of thinning out and "relaxing" your pattern for a while.

## Looper



As its name implies, this Action loops a section of a sequence. The length of the loop (in steps) is set by the Steps knob. When the Looper is activated, the Loop cycle begins on whichever (Pitch) step happens to be active at that time. Once the number of steps is reached, the loop begins again. This continues until the Looper button (or key) is released. Upon release, the sequence continues where it would have been if the Looper had not been activated. In other words, instead of just finishing the loop and continuing forward in the sequence, releasing the Looper brings the sequence position right back in step. This can be very useful for jumping in and out of melodic riffs or harmonic progressions without missing a beat.

## Slow Down



Think of the Slow Down Action as a handbrake for your sequence. When activated, it progressively slows the speed of the sequence down. The rate of slowing is set with the Slew Rate knob. Turn the knob to the left for a very gradual and long "decelerando" and turn to the right for quicker slow downs.

## Retrigger



Use the Retrigger Action to retrigger all the sequencers at once. Retrigger forces all the sequencers back to their first step while maintaining the step speed. When you release Retrigger, the sequences continue where they would have been if they had not been retriggered. This behavior is similar to that of the Looper Action.

[BACK TO TABLE OF CONTENT](#)

## Half Speed



As its name implies, Half Speed doubles the length of time between each step for all sequencers and creates a half-tempo feeling.

## Manual Step



This action button overrides the clock and triggers the sequencer one step at a time. Activate the button to stop the sequence; you can then manually move forward in the sequence using the Pattern Keys and the Pitch Keys one step at a time.

## Mute




The Mute Action mutes all notes, without stopping the sequencer. This is the same as sending a series of zeroes from the velocity sequencer. As with Looper and Retrigger, the sequencers continue to run when Mute is activated.

## Start/Stop Button



The Stop/Start Button turns the internal sequencer clock on and off. When lit, it indicates that either the internal or the host clock is running and the sequencers are on.

## Pattern Sequencer



This module is the top-level sequencer which determines which pattern will be played and how long that pattern will be played. A pattern consists of all sequences (Pitch, Velocity, Gate Time, Performance, Modulation) and their settings.

The Pattern Sequencer plays up to 16 different patterns in any order. In addition, each pattern can be repeated up to 16 times before moving on to the next one.

You can think of each pattern as a kind of snapshot of all the sequences visible in the Thesys window at any one time.

## **on/off**

When off, the currently displayed pattern will simply be looped continuously, without switching to another pattern. When activated, the Pattern Sequencer steps through the patterns determined by Pattern Sequencer Parameters:

## **Loop Bar**

Determines the total length of the Pattern Sequencer sequence. As with any step sequencer, after playing the last step in its sequence, the Sequencer will loop back to the beginning and continue playing through the pattern steps in order. The Pattern Length bar can be extended to the left or right and moved from the center.

## **Pattern Change Speed**

The note value input of the Pattern Speed Control determines how long a pattern is played before either repeating (see "Number of Repeats" below) or moving on to the next Pattern. Setting this value to a quarter note (one beat per change) will result in extremely frequent Pattern changes (at BPM=120, this would be twice per second!). In most cases, you will probably set this to at least a whole note (four beats per change) or more. The maximum value is four whole notes = 16 beats.

## **Pattern Select**

Pattern Select determines which Pattern is played on that particular step. Patterns can be played and repeated in any order. This makes it possible to set up repeating song structure elements (refrains, bridges, choruses, breaks, etc.) in your performances or productions.

## **Number of Repeats**

You can repeat a Pattern step up to 16 times. With a low Pattern Change Speed (see above) and a large number of repetitions, Patterns can be made to run a long time before moving on to the next Pattern step.

## Keyboard Control Section



The Keyboard Control Section offers you extensive live-performance-oriented control over Thesys. Here you can select a Pattern, trigger an Action, or transpose sequences up or down by hitting the corresponding key on your MIDI keyboard/controller. The keys can also be triggered by pressing on them with your finger.

Note that the Keyboard Control Section is split into three distinct key ranges, each with a different function: Pattern Select, Action Section, and Pitch.

There are two keyboard mappings available. Select the keyboard mode with the triangle icon above the keyboard. The standard mapping offers all Patterns and Actions and a +/- 12 semitone transposition zone. The extended Pitch range offers transposing by +/-24 semitones. Pattern- and Action Keys are still available, 2 octaves below the standard mapping.

You can shift these control keys up or down your keyboard, depending on the MIDI In transpose control in the Global MIDI Settings section of Thesys. You might consider routing a dedicated keyboard through an unused MIDI channel into Thesys so that playing notes (melodies, chords) on your master keyboard don't affect the control aspects of Thesys.

### Keyboard Control Quantization Value

Here you can choose a quantization value for Keyboard Control input. For example, if you want to trigger the Looper, but make sure it starts right on the beat, choose the quarter note symbol. Or, if you want to transpose your sequence at the beginning of the measure and don't want to miss a beat, set the value to whole notes.

### Pattern Select

Each of the sixteen keys in this range corresponds to one of the sixteen Patterns. Play the corresponding key with your finger or on your MIDI controller to trigger or change Patterns.

Pattern Select should not be confused with the [Pattern Edit Selector](#) which is for editing patterns, not selecting them to play.

### Action Section (Keys)

The Action Section of the keyboard shows the keyboard mapping of the Action Keys on your MIDI controller/keyboard. For a detailed description of each Action, see the Action Section description above.

[BACK TO TABLE OF CONTENT](#)

## Pitch Transposition

In addition to selecting Patterns, triggering Actions, and Transposing, the keyboard can also be used to start or stop the sequencer. You can use the Pitch Transposition keys (hit C3 or "0" to start/stop without transposition) or the Pattern Select keys to do this depending on the setting of the "Triggered By" switch in the Global MIDI Settings section (see above).

[BACK TO TABLE OF CONTENT](#)

## Sequencer Section

### Sequencer Preset



The Sequencer Preset Manager located at the very top of the Sequencer area of Thesys. Here you can load, save, and step through presets (using the arrow buttons). Each preset can contain up to 16 different patterns. In addition, a preset contains MIDI Settings and Action Section knob settings (Time, Threshold, Steps, and Slew Rate).

All other parameters are stored in individual Patterns within the preset.

Note that the Synthesizer Section has its own Preset Manager for loading Synthesizer presets (see below) and works independently from the Sequencer Preset Manager.

### Preset vs. Pattern

It is important to be clear on the difference between Sequencer Presets and Patterns. While Presets represent the highest level of the "parameter hierarchy," you can change practically all parameters of the Sequencer Section by changing Patterns.

This is because each Pattern contains the information stored in the five sequencers: Pitch, Velocity, Gate Time, Performance, and Modulation (see above: "Pattern Sequencer"). In addition, a Pattern contains the root key, scale, sequencer play direction, master tempo settings, modulation CC assignments, and the swing factor. All of these parameters can change when changing from one pattern to another (either by manually keying the change or by using the Pattern Sequencer). This gives you an immense amount of real-time control and expressive possibility over your music.

### Global Sequencer Controls



### Copy & Paste



The Copy button copies the entire sequence. After copying, choose another preset slot, then press the Paste button.

## Global Shift



The Global Shift button moves the steps located within the corresponding sequencer's Loop either left, right, up, or down (for changing Loop length, see below).

## Random



The Random button creates a complete random situation. The Min/Max controls define the randomize amount. If Max is set lower than Min, values will be created within the difference.

## Pattern Edit Selector



All the information contained in the five sequencers can be stored as a Pattern. Up to sixteen Patterns can be stored in a single preset.

The Pattern Edit Selector allows you to edit each of these patterns individually.

Press on the Pattern you wish to edit (the Pattern Edit Selector button for that Pattern turns blue) and make the desired changes. When you are finished editing, press on the Pattern Edit Select Button again. Once you have created different Patterns, you can trigger them automatically with the Pattern Sequencer (see below). You can also trigger different Patterns manually by pressing on the Pattern Select on the Keyboard Control Layout (at the bottom of the Keyboard) or by playing the corresponding keys on your MIDI keyboard. Use the Pattern Edit Selector only for editing patterns, not for triggering them (because of the toggle-editing behavior). For Pattern triggering, use the Pattern Select keys in the Keyboard Control Section by either pressing on them or using your MIDI keyboard controller (see above: "Keyboard Control Section").

## Common Controls and Functions

### General Editing Features




A number of editing features have been implemented for the sequencer areas:

- Press and drag on a step to create or change a value.
- Press and hold **Fine** & drag on a step to edit for finer adjustments.
- Press and hold **Linear** to create a straight line across all other steps.
- Press and hold **All** & drag a step to move the whole sequence up or down.
- Press and hold **Midi Learn** & press on a step to assign/clear a CC

The performance section features advanced touch modes as well:

- Long-press to delete steps.
- Press and hold **Fine** & move an active step to spread (copy) that value with the finger.
- Press and hold **Linear** to increase a step value.
- Press and hold **Midi Learn** & press on a step to assign/clear a CC

### Step Direction and Interval



Pressing on the Step Direction and Interval control opens up a drop-down menu with the following choices:

Forward: Plays the sequence from left to right. This is the default setting.

[BACK TO TABLE OF CONTENT](#)

- Backward:** Plays the sequence from right to left.
- Random:** Plays the steps in a random order.
- Each 2nd:** Plays every other step. For sequences with an even number of steps, only steps 1, 3, 5... etc. will be played. For sequences with an odd number of steps, the first run through the sequence will be as above (1, 3, 5... etc.), but on the first repeat, steps 2, 4, 6... will be played.
- Each 3rd:** Same as Each 2nd, but instead one out of every three steps will be played.
- Each 4th:** Same as Each 2nd and Each 3rd, but instead one out of every four steps will be played.

Note that if the Loop switch in the Sequencer Settings section is set to Global, only the Pitch Sequencer gives you a choice of direction and interval, since in this case, the Pitch Sequencer (and its Loop) act as a "Master Sequencer" for all the other sequencers.

If you desire individual Step Direction and Interval control for each sequencer, then set the Loop switch to "Individual."

### Step Shift Control



The Step Shift Control moves the steps in the looped area one step forward (right), back (left), up, or down. In the performance sequencer, you may only move the sequence forward (right) or back (left).

### Copy and Paste



Copies the steps in the looped area (as determined by the sequencer's Loop Bar (see below). Use the Sequence Length Bar as a way of selecting the part of the sequence you want to copy. Then, move the bar to the area of the sequence where you would like to paste the copied part of the sequence.

This can be very useful in duplicating short riffs or patterns within the entire sequence.

A nice feature makes it easier to copy and paste several sequences at once: The Pitch sequencer, the Performance Sequencer and the Velocity, Gate Time and Modulation Sequencers work on individual « Copy & Paste Layers » .

This makes it possible :

1) to copy and paste the contents of Velocity, Gate time and Modulation Sequencers between each other ;

2) to copy and paste the Pitch, Performance and Velocity OR Modulation Sequencers at once. Therefore just set the loop bar to define the sequence range you like to copy, then choose another preset slot and press the Paste button.

You will now see that each sequencer content has been copied on its individual « Copy & Paste Layer ».

### Reset, Random and Mutate




Reset (x) sets the Sequencer to its default value.

Random (dice) creates a completely randomized situation.

Mutate (arrows) changes existing values.

### Loop Bar



The Sequence Loop bar is at the top of each of the five sequencers. It determines both the length of the sequence in steps and the beginning and start steps.

The Loop Bar also serves as the selection to be copied and then pasted within any given sequence (see "Copy & Paste" above).

Press and drag at the beginning or end of the bar to shorten or lengthen either end. Press and drag in the middle of the bar to move the entire bar without changing its length.

In the Global Settings, you can choose between individual Loop Bars for each sequencer, or a shared Loop Bar for all sequencers.

With the "Individual" setting in the Global Settings (Loop), rich patterns can be built quickly by staggering the lengths of the different sequencers. For example, you could have a five-step pitch sequence playing along with a seven-step gate sequence and an eleven-step performance sequence; together, they would result in a quasi non-repeating overall pattern. In addition, the "Individual" setting makes it possible to have one sequencer running forwards, another backwards, and yet another in random mode or skipping every other step, for example.

[BACK TO TABLE OF CONTENT](#)

## Global Sequencer Controls

The four Global Sequencer Controls are at the bottom left of the Sequencer window, just above the Pattern Select of the Keyboard Control Section.

The Copy & Paste buttons work just the individual sequencer Copy & Paste buttons (see above), except that the copying and pasting is for all of the entire sequences, not just the looped areas. In addition, you can copy and paste between presets and even different instances of Thesys.

To Shift button moves all the sequences either one step to the right or one step to the left each time you press on the corresponding arrow.

For a real adventure, press the Global Random button!

# Pitch



The Pitch Sequencer is the heart of any step sequencer, providing the pitch information for the synth or sampler being played.

Each sequencer step gives you 12 increments of pitch increase or decrease with respect to the root key. In a standard chromatic tone framework (12 half-steps in an octave), this means that you have a two-octave range (+/- 1 octave), which corresponds to the range in most standard step sequencers.

However, if you set the Mode to Major, for example, then an octave will be covered in seven steps, not twelve. In this case, if your root key is C3, the highest note (without octave transposition) on each step will be 12 scale steps above C3, or A4. Similarly, counting 12 scale steps below C3, you arrive at E1. Pentatonic (5-note) scales provide even more reach, because fewer scale steps (only five in this case) are required per octave.

## Root Key Set



The Root Key Set control establishes the root key of the Pitch Sequencer. This corresponds to the middle line along the window. It is also the note value of all the steps when the sequencer is reset (Reset button to the right of the various sequencers). Think of the root key as the key you want to play in. Used with the Scale Selector (see below), the root key can help you quickly build tonal sequences that automatically confine themselves to a particular scale, based on a particular root key for that scale.

## Scale Selector



The Scale Selector gives you a broad choice of automatic scaling of the Pitch Sequencer. If you do not want to be confined to a particular scale or mode, choose "Chromatic" and the Pitch Sequencer will behave like any normal pitch sequencer module. However, if you are building a pattern in, say, D minor, then setting the Root Key to "D" and the Scale Selector to "minor" will make sure that all the steps in the Pitch Sequencer will be part of a D minor scale.

In addition to major and minor scales, there is very large number of other scales. Experimenting with the different scale types can yield unexpected and interesting results.

## Recording Input Mode




Although the standard way of building patterns is drawing on the various sequencers with your finger, you might find it easier to use one of the recording input modes for creating pitch sequences which uses the MIDI notes produced by your MIDI keyboard/controller to record into the pitch sequencer.

The Recording Input Mode gives you a choice between Live and Step recording:

When the Record button is activated in Live mode, the pitches will be recorded in real time when you set Thesys in motion. In this case, each note you play will be quantized to the clock rate ( $\text{BPM} \times \text{note value} = \text{step rate}$ ). Depending on the length set in the Pitch Sequencer, the pattern will continue repeating and will record any incoming MIDI notes — overwriting notes which were recorded on previous passes — until you press Record again to stop the recording process or until the sequencer clock is stopped.

In Step mode, each time you play a note, Thesys records that note on the current step, advances to the next step, and then waits for you to play the next note. This is very useful for building complex patterns that may be difficult to play in real time.

## Note Name Display




Below each step is a Note Name Display which shows the note name of each step.

## Lock

Under the Note Name Display, the Lock buttons let you lock each individual step to prevent any further changes. Just press on the bar under the step(s) you would like to lock and a small red bar appears.

# Velocity



The Velocity sequencer provides the gate signal that triggers each step in the Pitch sequencer. The height of each step (amount of velocity) determines how loud the triggered note on that step will be played. If you are using Thesys to trigger an external synth, make sure that the external instrument or its preset also reacts to different velocities if you want this to be effective.

## Sequencer Area

The Velocity Sequencer default step value is 0 (on a scale of 0 to 127), which represents the lowest possible position of each step, producing no trigger on that step (no sound). Press and drag on each step to raise or lower velocity. Press and drag along multiple steps to create velocity curves along consecutive steps.

## Mute



Each Velocity Sequencer step has its own mute button represented by the dark area below the step. When pressed, a red "x" indicates that a step is muted. This is equivalent to setting the step to 0 velocity and is a handy way to quickly develop rhythms in your patterns.



# Performance



The Performance Sequencer is actually five sequencers in one: Octave, Bend, Chord, Roll, and Random, arranged in rows. The Performance Sequencer is the key to making your patterns vibrant and interesting by introducing quite a bit of variety in the way they are played.

## Octave



The Octave row shifts the pitch up or down one or two octaves. Press on a step to open the octave shift palette and then press again to choose. Long-press to reset any step.

## Bend



Pressing on a step in the Bend row opens a palette of twenty different pitch bend shapes and directions to choose from. This ranges from a simple bend up or down to multi-bends, which can create interesting pitch modulation effects (vibrato) over individual or multiple steps.


## Chord



A press on a step in the Chord row opens the Chord Palette with a vast choice of chord types and inversions (see [Chords](#) for a list of the chords available).

The chord is based on the current note in the pitch sequencer. In other words, if the pitch sequencer shows note C on a step with a minor chord on it, the resulting chord will be C minor.

## Roll



The Roll row provides a choice of 18 different articulation patterns for each step. The first row of patterns on the palette repeat the note within a three or four note subdivision. The second row performs the same rhythm, but instead of repeating notes, each successive note of the roll is transposed up the next scale step (depending on the scale set in the pitch sequencer). The third row of the palette behaves exactly the same except that the successive step repetitions are transposed down to the next scale step (also determined by the scale set in the pitch sequencer).

## Random



The Random sub-sequencer lets you randomize any of the following parameters: Pitch, Velocity, Trigger, Gate Time, Octave, Pitch Bend, Chord Major, Chord Minor, and Roll on any step(s) you choose. Any of the eight Modulation Track parameters may also be randomized. Used sparingly, the Random row can spice up your sequences without making them go completely berserk.

[BACK TO TABLE OF CONTENT](#)

# Modulation



The Modulation Sequencer allows you to modulate any available MIDI CC parameter. For example, you can send pan, filter cutoff, or even program change information to your external synthesizer. In addition, if you are just using the Built-in Synthesizer, you can also modulate a number of synth parameters as well.

The Modulation Sequencer consists of eight Modulation Tracks. These are selected by pressing on the column of eight buttons located just to the left of the Modulation Sequencer controls with the first track at the bottom and the eighth track at the top.


Each Track can have its own Loop settings (length, start, and end) and Play Direction. It is assigned to both an internal (Built-in Synthesizer) modulation target and an external MIDI CC number.

The modulator sequencer buttons light up in relation to the data they play back. Each modulation track can be deactivated independently. Use the “ All modulators off” Button below the modulations selectors to deactivate all modulators with one press.

## Internal Modulation

Each of the tracks is pre-assigned to a specific modulation target parameter in the built-in Synthesizer. If you press on the Modulation Track 1 (the lowest of the column of buttons to the left of the Modulation Sequencer), you'll see the internal assignment indicates "Level." Just to the right of that, a button can be pressed on (green) or off (dark grey) to activate or deactivate internal modulation for that track. The pre-assigned internal modulation parameters are: Level, Pan, Wave, Detune, Cutoff, Reso, Peak, and Delay Mix.

## MIDI CC number



Just above the Internal Modulation indicator is the external MIDI CC chooser. Press to open a drop down menu containing all of the MIDI CC numbers with Aftertouch and Program Change located in the last menu. The MIDI CC Modulation is organized in the same way as Internal Modulation, except that you can assign the different MIDI CC targets however you want to the eight Modulation Tracks.

Note that each Modulation Track contains the sequencer information (Loop parameters, direction, and values) for both the Internal Modulation AND the external MIDI CC data transmission. In other words, each track shares the same data for both internal and external modulation. In general, this should not make any difference because in most cases, you'll either be using the (internally modulated) built-in Synthesizer OR the Thesys to drive an external synthesizer.

### On/Off Button

Turn internal modulation of the built-in synthesizer on or off with the green indicator-button.

### MIDI Value

The MIDI values of each step are indicated at the bottom of each step of the Modulation Sequencer.

[BACK TO TABLE OF CONTENT](#)

## Built-in Synthesizer




Thesys is designed to be the ultimate MIDI sequencer used within a host environment. The MIDI output is typically used to drive a software synthesizer or sampler plugged into your host alongside Thesys, or even external hardware you might want to control as well.

However, when building patterns, at first you may not want to set up MIDI routing to a software instrument, but just need to get a general idea of how your pattern will sound. This is why we have created a simple built-in synthesizer.

To access the synthesizer controls, press on the loudspeaker icon along the upper edge of the Sequencer Section. This toggles to the synthesizer controls. These controls will be familiar to anyone having some experience with hardware or software synthesizers.

## Synthesizer Preset Manager



Located just under the Sugar Bytes logo, the Synthesizer Preset Manager works the same as the Sequencer Preset Manager. Simply press on the name of the preset to open the Preset Chooser in order to load or save a preset.

## On/Off



The Oscillator On/Off button is located in the upper right corner of the Synthesizer Control Area and activates or deactivates the internal synthesizer.

[BACK TO TABLE OF CONTENT](#)

## Oscillator Settings



### Level

Sets the volume level of the synthesizer output.

### Pan

Determines the position (panorama) in a left-right stereo field.

### Waveform

The Waveform knob morphs between triangle, square, and narrow square wave forms.

### Detune

The synthesizer oscillators generate two voices simultaneously; the Detune controls the frequency spread between the voices on a scale from 0 to 100%. When set in the middle, there is no detuning, when turned to the right or left, the voices are detuned with regards to one another, creating a thicker sound.

### Volume Envelope

The volume envelope can be formed using the classic parameters Attack time, Decay time, Sustain level, and Release time.

### Filter



The built-in synthesizer also has a low pass filter module. The filter envelope determines the amount of time between the cutoff and the peak value. Envelope output 0 represents the cutoff value, envelope output 1 represents the peak value. This feature ensures that filter modulation always occurs within the valid cutoff range to avoid clipping. If cutoff and peak (which usually is the envelope amount) would be just added, you would easily get above the valid cutoff range and so clipping would occur.

One way to think of these values is that cutoff is the minimum frequency and peak is the maximum frequency, and the envelope modulates the output between these two values.

### **Cutoff**

Determines the overall cutoff frequency of the filter. It is the base value of the filter envelope, with Peak being the highest possible value.

### **Reso(nance)**

Resonance sets the amount of Q or resonance of the cutoff frequency. Setting this control completely to the left will produce a very smooth, non-resonant sounding filter effect. As Resonance increases, the cutoff frequency becomes more pronounced, eventually becoming self-resonating (whistling sound).

### **Peak**

Peak is the upper frequency cutoff limit as determined by the filter envelope.

### **Attack**

The length of time required to reach the Peak frequency, as set by the Peak parameter.

### **Decay**

The amount of time to fall back from the Peak frequency.

### **Sustain**

The frequency held (between Peak and Cutoff) after Decay time and before Release.

### **Release**

The amount of time for the frequency to drop back down to the cutoff frequency level.

### **Delay**



The simple delay module provides separate delay time controls for the left and right stereo channels, a delay feedback control, and an effect mix control.

### **Delay L(eft) Delay R(ight)**

Delay time for the left and right stereo channels

## **Feedback**

Feeds the delayed signal back into the delay module input. Setting this to a higher level (to the right) increases the amount of delay (the number of echoes) that you hear before the signal dies out.

## **Mix**

Mixes the proportion of delayed signal (to the right: "wet") and unprocessed signal (to the left: "dry").

[BACK TO TABLE OF CONTENT](#)

## Appendix

All Scales available in the scale menu, with C as rootnote:

Chromatic:	C C# D D# E F F# G G# A A# B
Major:	C D E F G A B
Dorian:	C D D# F G A A#
Phrygian:	C C# D# F G G# A#
Lydian:	C D E F# G A B
Mixolydian:	C D E F G A A#
Aeolian:	C D D# F G G# A#
Locrian:	C C# D# F F# G# A#
General Bebop:	C D E F G G# A B
Harmonic Minor:	C D D# F G G# B
Melodic Minor:	C D D# F G A B
Major Pentatonic:	C D E G A
Minor Pentatonic:	C D# F G A#
Augmented:	C D# E G G# B
Blues:	C D# F F# G A#
Diminished:	C D D# F F# G# A B
JazzMinor:	C D D# F G A B
Whole Tone:	C D E F# G# A#
Bebop:	C C# D# F F# G G# A#
Minor Bebop:	C D D# E F G A A#
Arabian:	C D E F F# G# A#
Balinese:	C C# D# G G#
Enigmatic:	C C# E F# G# A# B
Gypsy:	C C# E F G A A#
Hindu:	C D E F G G# A#
Hngarian Minor:	C D D# F# G G# B
Hungarian Major:	C D# E F# G A A#
Japanese:	C C# F G G#
Jewish:	C C# E F G G# A#

Neapolitan Major: C C# D# F G A B  
 Neapolitan Minor: C C# D# F G G# B  
 Oriental: C C# D# F F# A A#  
 Persian: C C# E F F# G# B  
 Spanish 8 Tone: C C# D# E F F# G# A#

## Chords

All Chords available in the performance/ chord menu, with C a rootnote.

Maj Green



Major 6 Green



Major6+Green



Major 7 Green



Major 7+ Green



[BACK TO TABLE OF CONTENT](#)

Major 9 Green



Major Blue



Major 6 Blue



Major 6+ Blue



Major 7 Blue



Major 7+ Blue



Major 9 Blue



[BACK TO TABLE OF CONTENT](#)

Major Yellow



Major 6 Yellow



Major 6+ Yellow



Major 7 Yellow




Major 7+ Yellow




Major 9 Yellow



Major White



Major 6 White




Major 6+ White



Major 7 White




Major 7+ White




Major 9 White



Minor Green




Minor 6 Green




[BACK TO TABLE OF CONTENT](#)


Minor 6+ Green




Minor 7 Green



Minor 7+ Green



Minor 9 Green



Minor Blue



Minor 6 Blue



Minor 6+ Blue



Minor 7 Blue



Minor 7+ Blue



Minor 9 Blue



Minor Yellow



Minor 6 Yellow



Minor 6+ Yellow




Minor 7 Yellow



[BACK TO TABLE OF CONTENT](#)


Minor 7+ Yellow




Minor 9 Yellow




Minor White




Minor 6 White




Minor 6+ White



Minor 7 White




Minor 7+ White




[BACK TO TABLE OF CONTENT](#)

Minor 9 White



Diminished / Vermindert



Quint / Quinte




Augmented / Übermässig



Fourth / Quarte



Cluster / Traube



Quint Stack / Quintschichtung



[BACK TO TABLE OF CONTENT](#)

## FAQ

Have I found a bug?

Please write to [support@sugar-bytes.de](mailto:support@sugar-bytes.de)

## Contact

Sugar Bytes GmbH | Made of passion

Robert Fehse, Rico Baade | Greifswalder Str. 29 | 10405 Berlin, Germany

phone:+493060920395 | Str.-Nr. 37/207/21266 | HR-Nr. HRB 124199 B

[info@sugar-bytes.de](mailto:info@sugar-bytes.de) | [www.sugar-bytes.com](http://www.sugar-bytes.com)

[BACK TO TABLE OF CONTENT](#)